

Exclaimer Signature Manager Outlook Edition Release Notes

Version Number

The current version number for this product is: 3.0.4

System Requirements - Server

Hardware	Minimum Requirements	Recommended Requirements
CPU	x86 or x64 architecture-based computer. Intel Itanium family IA64 processor are not supported.	x86 or x64 architecture-based computer. Intel Itanium family IA64 processor are not supported.
Memory	2GB	4GB
Disk Space	350 MB	500MB
Screen Resolution	1024 x 768	1152 x 864 or higher

Software	Minimum Requirements
Operating Systems	Windows Server 2003 x86 (including all service pack levels). Windows Server 2003 R2 x86 and x64 (including all service pack levels). Windows Server 2008 x86 and x64 (including all service pack levels). Windows Server 2008 R2 (including all service pack levels). Windows Server 2012. Windows Server 2012 R2. Windows Small Business Server 2003. Windows Small Business Server 2008. Windows Small Business Server 2011. Windows XP x86 and x64 (including all service pack levels). Windows Vista x86 and x64 (including all service pack levels). Windows 7 x86 and x64 (including all service pack levels). Windows 8 x86 and x64. Windows 8.1 x86 and x64. Windows 10 x86 and x64.
Microsoft .Net Framework	Microsoft .Net Framework 4.0 or 3.5.1
Active Directory	Domain and Forest functional level of Windows Server 2003 and above.

System Requirements – Client (ExSync.exe)

Hardware	Minimum Requirements	Recommended Requirements
CPU	x86 or x64 architecture-based computer. Intel Itanium family IA64 processor are not supported.	x86 or x64 architecture-based computer. Intel Itanium family IA64 processor are not supported.
Memory	512MB	1GB
Disk Space	20MB	20MB

Software	Minimum Requirements
Operating Systems	Windows Server 2003 x86 (including all service pack levels). Windows Server 2003 R2 x86 and x64 (including all service pack levels). Windows Server 2008 x86 and x64 (including all service pack levels). Windows Server 2008 R2 (including all service pack levels). Windows Server 2012. Windows Server 2012 R2. Windows Small Business Server 2003. Windows Small Business Server 2008. Windows Small Business Server 2011. Windows XP x86 and x64 (including all service pack levels). Windows Vista x86 and x64 (including all service pack levels). Windows 7 x86 and x64 (including all service pack levels). Windows 8 x86 and x64. Windows 8.1 x86 and x64. Windows 10 x86 and x64.
Microsoft Outlook	Outlook 2003 (including all service pack levels). Outlook 2007 (including all service pack levels). Outlook 2010 x86 and x64 (including all service pack levels). Outlook 2013 x86 and x64. Outlook 2016 x86 and x64.
Outlook Web Access (OWA) \ Outlook Web Apps	Outlook Web Access 2003. Outlook Web Access 2007. Outlook Web Apps 2010. Outlook Web Apps 2013. Outlook Web Apps 2013. Office 365.

Downloading

Please refer to the following link on the Exclaimer website:

<http://www.exclaimer.com/signature-manager-outlook-edition/download>

Installing

Download and run the 'Signature Manager Outlook Edition 3.0.4' installation file 'setup.exe'. An MSI is available from support by contacting support@exclaimer.com.

Uninstalling

Uninstall can be achieved via the 'setup.exe' or MSI for the currently installed version of 'Signature Manager Outlook Edition 3.0' or via 'Add/Remove Programs' in Windows 2003 and Windows XP or 'Programs and Features' in Windows 2008, Windows 2012, Windows Vista, Windows 7, Windows 8 and Windows 10.

The configuration files are located in the following folder and will not be removed as part of the uninstall process:

Operating System	File Location
Windows Server 2003 x86 and x64 Windows Server 2003 R2 x86 and x64 Windows Small Business Server 2003 Windows XP x86 and x64	\\Documents and Settings\\All Users\\Application Data\\Exclaimer Ltd\\Signature Manager
Windows Server 2008 x86 and x64 Windows Server 2008 R2 Windows Server 2012 Windows Server 2012 R2 Windows Small Business Server 2008 Windows Small Business Server 2011 Windows Vista x86 and x64 Windows 7 x86 and x64 Windows 8 x86 and x64	\\ProgramData\\Exclaimer Ltd\\Signature Manager

The uninstall process will not lose any of your configuration or settings. However, as a backup precaution you may wish to export your configuration.

Export Steps

1. Open the Exclaimer Console
2. Select the 'Exclaimer' node
3. Open the 'Action' menu
4. Select 'Export Configuration...'
5. Select a location and filename for the export
6. Press Save

This will export all your settings including all your templates and licensing data.

Upgrading

Upgrading can be achieved via the 'setup.exe' which will perform an in-place upgrade.

Fixed Issues

- Inline images referenced via UNC paths were not embedded in signatures.

Known Issues

- Unable to determine Share and Security permissions on a DFS namespace share running in Windows Server 2008 mode.
- Security permissions are not applied correctly if the Deployment share is on a DFS namespace on Server 2008 but running in 2000 mode.